



# First Time Setup (Step 2)

PRODUCTS USED  
DFX Print Optimizer

For DFX Print Optimizer


To open the software and begin setup:

- Open the File Explorer window on your computer. 
- Navigate to Local Disk (C:) > Digital Heat FX Print Optimizer v2
- Scroll down to locate the **PSQueue** application file from this folder and double click on it to open the software for the first time.




Choose how you would like the measurements to be displayed. Then, press **OK**.


**NOTE:** You can change this any time in the software by navigating to *Tools>Options*.



The *Compass* window will also open at this time, which is essentially the "Help" section of the software. You may close that window at this time to continue setup.




Click **Next**.




The software now would like you to connect your device. At this time, ensure the printer is plugged in (both the power and USB cords) and turned on.

Then, click **Next**.



Now, you will assign the printer to the software. Click the **Install Printer** button.



Create Queue Wizard

**Printer Defaults**

Assign a default printer for this production queue.

Select the default printer, print mode, and output port for this queue:

Printer:


Port: FILE  ...

Print mode:  ...

To ensure consistency in color management, only select Default if no specific print mode exists.

Back Next Cancel

Select the printer you have purchased and would like to install and then click **OK**.



Install Printer

Select a printer from the list you want Digital Heat FX Print Optimize v2 to support


Search:  Clear

Select none **Items selected: 0**

DFX 8432WT v2
DFX 920WT v2
DFX Pro9541WT
UniNet iColor 550

OK Cancel

Select **Search for new printer package(s) from DVD or cloud server** AND **Search Cloud server for printer package(s)** and then click **Next**.



Add Printer

Device Package Search

Search for new printer package(s) from DVD or Cloud server.

Search Cloud server for printer package(s).  
Internet access required for this search to take place


Search DVD.  
Please insert Printer DVD supplied with Rip Software

Don't search automatically, I will choose the search location  
Select this option if you would like to select a printer package from a specific location. This printer package may not be the most recent version available.

Browse...

Back Next Cancel

When the device package update is complete and you get the three green checkmarks on the left of the screen, click **Next**.



Add Printer

Copying Device Packages

Overall copy progress

✓ Installation Complete

Download progress

✓ DFX28432.1.22.RQ.pkg64 From updater.cadlink.com

Downloaded: 4.42 MB copied in 0 seconds  
Transfer rate: 70.39 MB/Sec


Extraction progress

✓ Extraction Complete


Device package update is complete. Click 'Next' to continue.

Next

This screen will ask you to set the Port for the installed printer. You can skip this step, as we will set the port in **Step 3** of the process. Simply leave the setting the way that it is and click **Next**.



The printer setup process is now completed and you can click **Finish**. The software will now open.



You have now completed **Step 2** of the installation process of the Print Optimizer software.

**For additional support, please contact [support@coldesi.com](mailto:support@coldesi.com) or open a ticket at <https://support.coldesi.com/open-a-ticket/>.**